

ASDM Online

10-Digit Dialing Instructions

10-digit dialing is NOT 11-digit dialing. If your computer dials 1-724-639-0259 (11-digits) this may be treated as a long distance phone call and the call might be handed off to your long distance carrier and you could be paying per minute charges.

Windows 95/98

1. Make sure you are not connected to the Internet. Then double Click on "My Computer".
2. Double Click on "Control Panel".
3. Double Click on the "Modems". Then click once on the "Dialing Properties". In the box after "To access an outside line, first dial" enter 724 for local calls.
4. Click the "Ok" to exit out of each window and save settings.

Windows ME

1. Click on the "Start Button", click "Setting" then click on "Control Panel".
2. Left-click "View all Control Panel Options".
3. Double Click on the "Dial-Up Networking" option. Then click once on the ASDM Online icon so that it is highlighted. Then left-click on 'File' then 'Properties'.
4. Make sure the box next to "Use area code and dialing properties" is checked. (Left-click once on it if not checked.) When the box is checked, the area code should now be visible (not faded out). Make sure the area code is 724. Click 'OK'.
5. Double-click the ASDM Online icon. You should now be able to left-click the 'Dial Properties' button. On the window that opens up, click on the "Area Code Rules" button that is located beside the area code.
6. Select the "Always dial the area code" box that is located towards the top.
7. Click the "Ok" to exit out of each window and save settings.

Windows 2000

1. Click on the "Start Button", click "Setting" then click on "Control Panel".
2. Double click on "Phone and Modem Options".
3. Click on the "Edit" button.
4. Click on the "Area Code Rules" tab at the top of the screen.
5. Click on "New"
6. Type in the correct area code for the access number that you dial where it says "Area Code".
7. Choose "Include the prefixes in this area code".
8. Put a check mark in the box near the bottom where it says, "Include the Area Code". This is located toward the bottom.
9. Click "Ok" to exit out of each window and save settings.

Macintosh

1. Click on the "Apple".
2. Choose the "Control Panels" option.
3. Choose "PPP" or the "remote access" option.
4. Expand the window by clicking on the triangle. (Ignore this if you already see the place to type the phone number.)
5. Type in the correct access number including the area code in the "Number" box. (You may only need to click in front of the existing number and type your area code in front of it.)
6. Click "Done" to exit out and to save settings.

WebTV

1. Add the area code to the phone number in your WebTV setup (Do not add the 1 in front of the area code!).

*** Remember!!! Do not put a (1) before the area code. If you put a (1) before the area code, you could incur long distance charges. ***